

21.5. wave — Read and write WAV files

Source code: [Lib/wave.py](#)

The `wave` module provides a convenient interface to the WAV sound format. It does not support compression/decompression, but it does support mono/stereo.

The `wave` module defines the following function and exception:

`wave.open(file[, mode])`

If *file* is a string, open the file by that name, otherwise treat it as a seekable file-like object. *mode* can be any of

'r', 'rb'

Read only mode.

'w', 'wb'

Write only mode.

Note that it does not allow read/write WAV files.

A *mode* of 'r' or 'rb' returns a `Wave_read` object, while a *mode* of 'w' or 'wb' returns a `Wave_write` object. If *mode* is omitted and a file-like object is passed as *file*, *file.mode* is used as the default value for *mode* (the 'b' flag is still added if necessary).

If you pass in a file-like object, the wave object will not close it when its `close()` method is called; it is the caller's responsibility to close the file object.

`wave.openfp(file, mode)`

A synonym for `open()`, maintained for backwards compatibility.

exception `wave.Error`

An error raised when something is impossible because it violates the WAV specification or hits an implementation deficiency.

21.5.1. Wave_read Objects

`Wave_read` objects, as returned by `open()`, have the following methods:

Wave_read.close()

Close the stream if it was opened by [wave](#), and make the instance unusable. This is called automatically on object collection.

Wave_read.getnchannels()

Returns number of audio channels (1 for mono, 2 for stereo).

Wave_read.getsampwidth()

Returns sample width in bytes.

Wave_read.getframerate()

Returns sampling frequency.

Wave_read.getnframes()

Returns number of audio frames.

Wave_read.getcomptype()

Returns compression type ('NONE' is the only supported type).

Wave_read.getcompname()

Human-readable version of [getcomptype\(\)](#). Usually 'not compressed' parallels 'NONE'.

Wave_read.getparams()

Returns a tuple (nchannels, sampwidth, framerate, nframes, comptype, compname), equivalent to output of the `get*()` methods.

Wave_read.readframes(*n*)

Reads and returns at most *n* frames of audio, as a string of bytes.

Wave_read.rewind()

Rewind the file pointer to the beginning of the audio stream.

The following two methods are defined for compatibility with the [aifc](#) module, and don't do anything interesting.

Wave_read.getmarkers()

Returns None.

Wave_read.getmark(*id*)

Raise an error.

The following two methods define a term “position” which is compatible between them, and is otherwise implementation dependent.

`Wave_read.setpos(pos)`

Set the file pointer to the specified position.

`Wave_read.tell()`

Return current file pointer position.

21.5.2. Wave_write Objects

Wave_write objects, as returned by `open()`, have the following methods:

`Wave_write.close()`

Make sure *nframes* is correct, and close the file if it was opened by `wave`. This method is called upon object collection.

`Wave_write.setnchannels(n)`

Set the number of channels.

`Wave_write.setsampwidth(n)`

Set the sample width to *n* bytes.

`Wave_write.setframerate(n)`

Set the frame rate to *n*.

`Wave_write.setnframes(n)`

Set the number of frames to *n*. This will be changed later if more frames are written.

`Wave_write.setcomptype(type, name)`

Set the compression type and description. At the moment, only compression type NONE is supported, meaning no compression.

`Wave_write.setparams(tuple)`

The *tuple* should be (*nchannels*, *sampwidth*, *framerate*, *nframes*, *comptype*, *compname*), with values valid for the `set*()` methods. Sets all parameters.

Wave_write.tell()

Return current position in the file, with the same disclaimer for the [Wave_read.tell\(\)](#) and [Wave_read.setpos\(\)](#) methods.

Wave_write.writeframesraw(*data*)

Write audio frames, without correcting *nframes*.

Wave_write.writeframes(*data*)

Write audio frames and make sure *nframes* is correct.

Note that it is invalid to set any parameters after calling `writeframes()` or `writeframesraw()`, and any attempt to do so will raise [wave.Error](#).